

Release Notes GC-PrevuePlus v12.2

Table of Contents

- ENHANCED FEATURES 2**
 - RS-274X IMPORT 2
 - ON LINE HELP 2
- ITEMS FIXED SINCE V12.1.4..... 3**

Enhanced Features

RS-274X import

A switch has been added to allow the correct image to be presented if the RS-274X file being imported incorrectly assumes the Macro21 primitive center is the point of rotation. The updated RS-274X specification now explicitly describes the correct interpretation of custom aperture macros and it is expected that this option will be very rarely needed by users.

On Line Help

All products have finally had their On Line Help files updated to the HTMLHelp format, allowing the Help file to appear within the product again.

Items Fixed since v12.1.4

This list is customer reported issues fixed for this release.

#118 Modified the code for both the Multi-up Recognizer function and the Advanced Scan and Replace function to avoid the creation of a temporary file in the installation directory. Unless the application was being run in Administrator mode, this caused problems in Windows7 operating system.

#114 Added an option allowing the correct handling of incorrectly formatted RS-274X data.

#103 Missing and duplicated toolbar buttons have been added or modified to correctly present a valid toolbar button for all functions.